


Viewing data with ArcExplorer2

Click on the Add Theme Button (+)




Navigate to the location of the data on the CD or computer.


Select the imagery, (.sid file) example: ortho_1-1_1n_ok135.sid, click Add Theme.

Select the index, (.shp file), example: ortho_1-1_1n_ok135.shp, click Add Theme.


Click Close.




To view the data click the box next to each layer name.




To view the imagery under the index data layer double click on the index name. This will make it the active layer and open the Theme Properties menu.




Select Style, Transparent fill, and click Apply.




To change the color and size of the index lines enter a new number in the Size box and select a color from the Outline color box. Click OK.




To zoom in on the imagery click on the magnifying glass button and select the area of interest. To move the image click the hand button and while pressing the left mouse button move the image.




To view the index information click on the button of a circle with the letter i. Next click on any part of the index and a table will appear with the information for that particular area. To get the information for other areas click on the area of interest.




To display the scale bar, scale, and coordinates set the Scale Bar Properties and the click on the Display Scale Bar.



To print a map select File, Print... Type in a name for the map and select printer.



For additional instructions on how to use the ArcExplorer2 software click on Help.



**For additional information contact:
USDA-FSA
Aerial Photography Field Office
2222 West 2300 South
Salt Lake City, UT 84119-2020**

801-975-3500

Hwww.apfo.usda.govH

